



# DHCP—Static Mapping

---

The DHCP—Static Mapping feature enables assignment of static IP addresses without creating numerous host pools with manual bindings by using a customer-created text file that the DHCP server reads. The benefit of this feature is that it eliminates the need for a long configuration file and reduces the space required in NVRAM to maintain address pools.

## Feature History for the DHCP—Static Mapping Feature

---

Release	Modification
12.3(11)T	This feature was introduced.

---

## Finding Support Information for Platforms and Cisco IOS Software Images

Use Cisco Feature Navigator to find information about platform support and Cisco IOS software image support. Access Cisco Feature Navigator at <http://www.cisco.com/go/fn>. You must have an account on Cisco.com. If you do not have an account or have forgotten your username or password, click **Cancel** at the login dialog box and follow the instructions that appear.

## Contents

- [Information About DHCP—Static Mapping, page 1](#)
- [How to Configure DHCP—Static Mapping, page 2](#)
- [Configuration Examples for DHCP—Static Mapping, page 6](#)
- [Additional References, page 6](#)
- [Command Reference, page 7](#)

## Information About DHCP—Static Mapping

To configure this feature, you should understand the following concept:

- [DHCP Database, page 2](#)

## DHCP Database

A DHCP database contains the mappings between a client IP address and hardware address, referred to as a binding. There are two types of bindings: manual bindings that map a single hardware address to a single IP address, and automatic bindings that dynamically map a hardware address to an IP address from a pool of IP addresses. Manual (also known as static) bindings can be configured individually directly on the router or, by using the DHCP—Static Mapping feature, these static bindings can be read from a separate static mapping text file. The static mapping text files are read when a router reloads or the DHCP service restarts. These files are read-only.

The read static bindings are treated just like the manual bindings, in that they are:

- Retained across DHCPRELEASEs from the clients.
- Not timed out.
- Deleted only upon deletion of the pool.
- Provided appropriate exclusions for the contained addresses, which are created at the time of the read.

Just like automatic bindings and manual bindings, the static bindings from the static mapping text file are also displayed by using the **show ip dhcp binding** command.

## How to Configure DHCP—Static Mapping

This procedure contains the following tasks:

- [Creating the Static Mapping Text File](#) (required)
- [Configuring the DHCP Server to Read the Static Mapping Text File](#) (required)

### Creating the Static Mapping Text File

Perform this task to create the static mapping text file. You will input your addresses in the text file, which is stored in the DHCP database for the DHCP server to read. There is no limit on the number of addresses in the file. The file format has the following elements:

- Time the file was created
- Database version number
- IP address
- Hardware type
- Hardware address
- Lease expiration
- End-of-file designator

See [Table 1](#) for more details about the format of the text file.

The following is a sample static mapping text file:

```
*time* Jan 21 2005 03:52 PM
*version* 2
!IP address Type Hardware address Lease expiration
10.0.0.4 /24 1 0090.bff6.081e Infinite
10.0.0.5 /28 id 00b7.0813.88f1.66 Infinite
10.0.0.2 /21 1 0090.bff6.081d Infinite
*end*
```

**Table 1 Static Mapping Text File Field Descriptions**

Field	Description
*time*	Specifies the time the file was created. This field allows DHCP to differentiate between newer and older database versions when multiple agents are configured. The valid format of the time is Mmm dd yyyy hh:mm AM/PM.
*version* 2	Database version number.
IP address	Static IP address. If the subnet mask is not specified, a natural mask is assumed depending on the IP address. There must be a space between the IP address and mask.
Type	Specifies the hardware type. For example, type “1” indicates Ethernet. The type “id” indicates that the field is a DHCP client identifier. Legal values can be found online at <a href="http://www.iana.org/assignments/arp-parameters">http://www.iana.org/assignments/arp-parameters</a> in the “Number Hardware Type” list.
Hardware address	Specifies the hardware address. When the type is numeric, it refers to the hardware media. Legal values can be found online at <a href="http://www.iana.org/assignments/arp-parameters">http://www.iana.org/assignments/arp-parameters</a> in the “Number Hardware Type” list. When the type is “id”, this means that we are matching on the client identifier. For more information about the client identifier, please see RFC 2132, <i>DHCP Options and BOOTP Vendor Extensions</i> , section 9.14, located at <a href="http://www.ietf.org/rfc/rfc2132.txt">http://www.ietf.org/rfc/rfc2132.txt</a> or the <b>client-identifier</b> command reference page located at <a href="http://www.cisco.com/univercd/cc/td/doc/product/software/ios124/124tcr/tiad_r/adr_a1ht.htm#wp1125872">http://www.cisco.com/univercd/cc/td/doc/product/software/ios124/124tcr/tiad_r/adr_a1ht.htm#wp1125872</a> If you are unsure what client identifier to match on, use the <b>debug dhcp detail</b> command to display the client identifier being sent to the DHCP server from the client.
Lease Expiration	Specifies the expiration of the lease. “Infinite” specifies that the duration of the lease is unlimited.
*end*	End of file. DHCP uses the *end* designator to detect file truncation.

## Configuring the DHCP Server to Read the Static Mapping Text File

Perform this task to configure the DHCP server to read the static mapping text file.

## Prerequisites

The administrator should create the static mapping text file in the correct format and configure the address pools before performing this task.

Before editing the file, you must disable the DHCP server using the **no service dhcp** command.

## Restrictions

The static bindings must not be deleted when a DHCPRELEASE is received or must not be timed out by the DHCP timer. The static bindings should be treated just like manual bindings created by using the **ip dhcp pool** command.

## SUMMARY STEPS

1. **enable**
2. **configure terminal**
3. **ip dhcp pool name**
4. **origin file url**
5. **exit**

## DETAILED STEPS

	Command or Action	Purpose
Step 1	<b>enable</b>	Enables privileged EXEC mode. <b>Example:</b> Router> enable <ul style="list-style-type: none"> <li>• Enter your password if prompted.</li> </ul>
Step 2	<b>configure terminal</b>	Enters global configuration mode. <b>Example:</b> Router# configure terminal
Step 3	<b>ip dhcp pool name</b>	Assigns a name to a DHCP pool and enters DHCP configuration mode. <b>Note</b> If you have already configured the IP DHCP pool name using the <b>ip dhcp pool</b> command and the static file URL using the <b>origin file</b> command, you must perform a fresh read using the <b>no service dhcp</b> command and <b>service dhcp</b> command.
Step 4	<b>origin file url</b>	Specifies the URL from which the DHCP server can locate the text file. <b>Example:</b> Router(config)# origin file tftp://10.1.0.1/static-bindings
Step 5	<b>exit</b>	Exits to global configuration mode. <b>Example:</b> Router(dhcp-config)# exit

## Examples

The following example shows the address bindings that have been configured:

```
Router# show ip dhcp binding

00:05:14:%SYS-5-CONFIG_I: Configured from console by console

Bindings from all pools not associated with VRF:
IP address Client-ID/          Ls expir   Type     Hw address           User name
10.9.9.4/8  0063.7363.2d30.3036.  Infinite  Static   302e.3762.2e39.3634. 632d.4574.8892.
10.9.9.1/24 0063.6973.636f.2d30.  Infinite  Static   3036.302e.3437.3165. 2e64.6462.342d.
```

The following sample shows each entry in the static mapping text file:

```
*time* Jan 21 2005 22:52 PM
!IP address      Type            Hardware address           Lease expiration
10.19.9.1 /24    id             0063.6973.636f.2d30.3036.302e.3437
10.9.9.4         id             0063.7363.2d30.3036.302e.3762.2e39.3634.632d  Infinite
*end*
```

The following sample debug output shows the reading of the static mapping text file from the TFTP server:

```
Router# debug ip dhcp server

Loading abc/static_pool from 10.19.192.33 (via Ethernet0):
[OK - 333 bytes]

*May 26 23:14:21.259: DHCPD: contacting agent tftp://10.19.192.33/abc/static_pool (attempt 0)
*May 26 23:14:21.467: DHCPD: agent tftp://10.19.192.33/abc/static_pool is responding.
*May 26 23:14:21.467: DHCPD: IFS is ready.
*May 26 23:14:21.467: DHCPD: reading bindings from
                         tftp://10.19.192.33/abc/static_pool.
*May 26 23:14:21.707: DHCPD: read 333 / 1024 bytes.
*May 26 23:14:21.707: DHCPD: parsing text line
*time* Apr 22 2002 11:31 AM
*May 26 23:14:21.707: DHCPD: parsing text line ""
*May 26 23:14:21.707: DHCPD: parsing text line
!IP address Type Hardware address Lease expiration
*May 26 23:14:21.707: DHCPD: parsing text line
"10.9.9.1 /24 id 0063.6973.636f.2d30.3036.302e.3437"
*May 26 23:14:21.707: DHCPD: creating binding for 10.9.9.1
*May 26 23:14:21.707: DHCPD: Adding binding to radix tree (10.9.9.1)
*May 26 23:14:21.707: DHCPD: Adding binding to hash tree
*May 26 23:14:21.707: DHCPD: parsing text line
"10.9.9.4 id 0063.7363.2d30.3036.302e.3762.2e39.3634.632d"
*May 26 23:14:21.711: DHCPD: creating binding for 10.9.9.4
*May 26 23:14:21.711: DHCPD: Adding binding to radix tree (10.9.9.4)
*May 26 23:14:21.711: DHCPD: Adding binding to hash tree
*May 26 23:14:21.711: DHCPD: parsing text line "Infinite"
*May 26 23:14:21.711: DHCPD: parsing text line ""
*May 26 23:14:21.711: DHCPD: parsing text line
!IP address Interface-index Lease expiration VRF
*May 26 23:14:21.711: DHCPD: parsing text line "*end*"
*May 26 23:14:21.711: DHCPD: read static bindings from
tftp://10.19.192.33/abcmp/static_pool.
```

# Configuration Examples for DHCP—Static Mapping

This section contains the following configuration example:

- [Configuring the DHCP Server to Read the Static Mapping Text File: Example, page 6](#)

## Configuring the DHCP Server to Read the Static Mapping Text File: Example

The following example shows how to restart the DHCP server, configure the pool, and specify the URL at which the static mapping text file is stored:

```
no service dhcp
service dhcp
ip dhcp pool abcpool
  origin file tftp://10.1.0.1/staticfilename
```



**Note** The static mapping text file can be copied to flash memory on the router and served by the routers tftp process. In this case, the IP address in the origin file line must be an address owned by the router and one additional line of configuration is required on the router:

---

**tftp-server flash staticfilename**

---

## Additional References

The following sections provide references related to the DHCP—Static Mapping feature.

## Related Documents

Related Topic	Document Title
DHCP overview and configuration	<a href="#">Cisco IOS IP Configuration Guide</a> , Release 12.3
DHCP commands: complete command syntax, command mode, command history, defaults, usage guidelines, and examples	<a href="#">Cisco IOS IP Command Reference, Volume 1 of 4: Addressing and Services</a> , Release 12.3T

## Standards

Standards	Title
No new or modified standards are supported by this feature, and support for existing standards has not been modified by this feature.	—

## MIBs

MIBs	MIBs Link
No new or modified MIBs are supported by this feature, and support for existing MIBs has not been modified by this feature.	To locate and download MIBs for selected platforms, Cisco IOS releases, and feature sets, use Cisco MIB Locator found at the following URL: <a href="http://www.cisco.com/go/mibs">http://www.cisco.com/go/mibs</a>

## RFCs

RFCs	Title
RFC 1700	<i>Assigned Numbers</i>
RFC 2131	<i>Dynamic Host Configuration Protocol</i>
RFC 2132	<i>DHCP Options and BOOTP Vendor Ext</i>

## Technical Assistance

Description	Link
The Technical Support & Documentation website contains thousands of pages of searchable technical content, including links to products, technologies, solutions, technical tips, and tools. Registered Cisco.com users can log in from this page to access even more content.	<a href="http://www.cisco.com/techsupport">http://www.cisco.com/techsupport</a>

## Command Reference

This section documents modified commands only.

- [debug ip dhcp server](#)
- [origin](#)

---

 debug ip dhcp server

## debug ip dhcp server

To enable Cisco IOS Dynamic Host Configuration Protocol (DHCP) server debugging, use the **debug ip dhcp server** command in privileged EXEC mode. To disable DHCP server debugging, use the **no** form of this command.

**debug ip dhcp server {events | packets | linkage | class}**

**no debug ip dhcp server {events | packets | linkage | class}**

Syntax Description	<b>events</b> Reports server events, such as address assignments and database updates.
<b>packets</b>	Decodes DHCP receptions and transmissions.
<b>linkage</b>	Displays database linkage information, such as parent-child relationships in a radix tree.
<b>class</b>	Displays DHCP class-based information.

---

Command Modes	Privileged EXEC
---------------	-----------------

Command History	Release	Modification
	12.0(1)T	This command was introduced.
	12.2(13)ZH	The <b>class</b> keyword was added.
	12.3(4)T	This command was integrated into Cisco IOS Release 12.3(4)T.
	12.3(8)YA	This command was integrated into Cisco IOS Release 12.3(8)YA.
	12.3(11)T	The output was enhanced to show the static mappings.

---

Examples	The following example shows a combination of DHCP server events and decoded receptions and transmissions:
----------	---

```
Router# debug ip dhcp server events
Router# debug ip dhcp server packets

DHCPD:DHCPOFFER received from client 0b07.1134.a029 through relay 10.1.0.253.
DHCPD:assigned IP address 10.1.0.3 to client 0b07.1134.a029.
DHCPD:Sending DHCPACK to client 0b07.1134.a029 (10.1.0.3).
DHCPD:unicasting BOOTREPLY for client 0b07.1134.a029 to relay 10.1.0.253.
DHCPD:DHCPOREQUEST received from client 0b07.1134.a029.
DHCPD:Sending DHCPACK to client 0b07.1134.a029 (10.1.0.3).
DHCPD:unicasting BOOTREPLY for client 0b07.1134.a029 to relay 10.1.0.253.
DHCPD:checking for expired leases.
```

The following example shows database linkage information:

```
Router# debug ip dhcp server linkage

DHCPD:child pool:10.1.0.0 / 255.255.0.0 (subnet10.1)
DHCPD:parent pool:10.0.0.0 / 255.0.0.0 (net10)
DHCPD:child pool:10.0.0.0 / 255.0.0.0 (net10)
DHCPD:pool (net10) has no parent.
```

```
DHCPD:child pool:10.1.0.0 / 255.255.0.0 (subnet10.1)
DHCPD:parent pool:10.0.0.0 / 255.0.0.0 (net10)
DHCPD:child pool:10.0.0.0 / 255.0.0.0 (net10)
DHCPD:pool (net10) has no parent.
```

The following example shows when a DHCP class is removed:

```
Router# debug ip dhcp server class

DHCPD:deleting class CLASS1
```

The following example shows the debug output when the configured pattern does not match:

```
Router# debug ip dhcp server class

DHCPD:Searching for a match to 'relay-information
0106000 400020202020800060009e80b8800' in class CLASS1
DHCPD:Searching for a match to 'relay-information 010600040002020202020800060009e80b8800' in
class CLASS1
DHCPD:Searching for a match to 'relay-information 0106000
```

The following example shows the debug output when you unconfigure a DHCP pattern in a DHCP class and then configure the pattern in the DHCP class:

```
Router# debug ip dhcp server class

DHCPD:pattern 'relay-information 123456' removed from class CLASS1
DHCPD:Added pattern 'relay-information 010600040002020202 0800060009e80b8800' for class
CLASS1
```

The following example shows the debug output when the configured pattern does match:

```
Router# debug ip dhcp server class

DHCPD:Searching for a match to 'relay-information
0106000 400020202020800060009e80b8800' in class CLASS1
DHCPD:input pattern 'relay-information 010600040002020202 0800060009e80b8800' matches
class CLASS1
DHCPD:input matches class CLASS1
```

The following example shows the debug output when static mappings are configured:

```
Router# debug ip dhcp server

Loading abc/static_pool from 10.19.192.33 (via Ethernet0): !
[OK - 333 bytes]

*May 26 23:14:21.259: DHCPD: contacting agent tftp://10.19.192.33/abc/static_pool (attempt
0)
*May 26 23:14:21.467: DHCPD: agent tftp://10.19.192.33/abc/static_pool is responding.
*May 26 23:14:21.467: DHCPD: IFS is ready.
*May 26 23:14:21.467: DHCPD: reading bindings from
tftp://10.19.192.33/abc/static_pool.
*May 26 23:14:21.707: DHCPD: read 333 / 1024 bytes.
*May 26 23:14:21.707: DHCPD: parsing text line "*time* Apr 22 2002 11:31 AM"
*May 26 23:14:21.707: DHCPD: parsing text line ""
*May 26 23:14:21.707: DHCPD: parsing text line

!IP address Type Hardware address Lease expiration.

*May 26 23:14:21.707: DHCPD: parsing text line
"10.9.9.1/24 id 0063.6973.636f.2d30.3036.302e.3437"
*May 26 23:14:21.707: DHCPD: creating binding for 10.9.9.1
*May 26 23:14:21.707: DHCPD: Adding binding to radix tree (10.9.9.1)
*May 26 23:14:21.707: DHCPD: Adding binding to hash tree
```

debug ip dhcp server

```
*May 26 23:14:21.707: DHCPD: parsing text line
"10.9.9.4 id 0063.7363.2d30.3036.302e.3762.2e39.3634.632d"
*May 26 23:14:21.711: DHCPD: creating binding for 10.9.9.4
*May 26 23:14:21.711: DHCPD: Adding binding to radix tree (10.9.9.4)
*May 26 23:14:21.711: DHCPD: Adding binding to hash tree
*May 26 23:14:21.711: DHCPD: parsing text line "Infinite"
*May 26 23:14:21.711: DHCPD: parsing text line ""
*May 26 23:14:21.711: DHCPD: parsing text line

!IP address Interface-index Lease expiration VRF.

*May 26 23:14:21.711: DHCPD: parsing text line "*end*"
*May 26 23:14:21.711: DHCPD: read static bindings from
tftp://10.19.192.33/smith/static_pool.
```

#### Related Commands

Command	Description
<b>debug dhcp</b>	Displays debugging information about the DHCP client and monitors the status of DHCP packets.
<b>debug ip ddns update</b>	Enables debugging for DDNS updates.
<b>host (host-list)</b>	Specifies a list of hosts that will receive DDNS updates of A and PTR RRs.
<b>ip ddns update</b>	Enables a host to be used for DDNS updates of A and PTR RRs.
<b>hostname</b>	
<b>ip ddns update method</b>	Specifies a method of DDNS updates of A and PTR RRs and the maximum interval between the updates.
<b>ip dhcp client update</b>	Enables DDNS updates of A RRs using the same hostname passed in the dns
<b>dns</b>	options by a client on an interface.
<b>ip dhcp-client update</b>	Enables DDNS updates of A RRs using the same hostname passed in the dns
<b>dns</b>	options by a client.
<b>ip dhcp update dns</b>	Enables DDNS updates of A and PTR RRs for most address pools.
<b>ip host-list</b>	Specifies a list of hosts that will receive DDNS updates of A and PTR RRs.
<b>show ip ddns update</b>	Displays information about the DDNS updates.
<b>show ip ddns update</b>	Displays information about the DDNS update method.
<b>method</b>	
<b>show ip dhcp server</b>	Displays DHCP server pool statistics.
<b>pool</b>	
<b>show ip host-list</b>	Displays the assigned hosts in a list.
<b>update dns</b>	Dynamically updates a DNS with A and PTR RRs for some address pools.

# origin

To configure an address pool as an on-demand address pool (ODAP) or static mapping pool, use the **origin** command in DHCP pool configuration mode. To disable the ODAP, use the **no** form of this command.

**origin {dhcp | aaa | ipcp | file *url*} [subnet size *initial size* [autogrow *size*]]**

**no origin {dhcp | aaa | ipcp | file *url*} [subnet size *initial size* [autogrow *size*]]**

Syntax Description	<b>dhcp</b> Specifies the Dynamic Host Configuration Protocol (DHCP) as the subnet allocation protocol. <b>aaa</b> Specifies authentication, authorization, and accounting (AAA) as the subnet allocation protocol. <b>ipcp</b> Specifies the IP Control Protocol (IPCP) as the subnet allocation protocol. <b>file <i>url</i></b> Specifies the external database file that contains the static bindings assigned by the DHCP server. The <i>url</i> argument specifies the location of the external database file. <b>subnet size <i>initial size</i></b> (Optional) Specifies the initial size of the first requested subnet. You can enter <i>size</i> as either the subnet mask (nnnn.nnnn.nnnn.nnnn) or prefix size (/nn). The valid values are /0 and /4 to /30. <b>autogrow <i>size</i></b> (Optional) Specifies that the pool can grow incrementally. The <i>size</i> argument is the size of the requested subnets when the pool requests additional subnets (upon detection of high utilization). You can enter <i>size</i> as either the subnet mask (nnnn.nnnn.nnnn.nnnn) or prefix size (/nn). The valid values are /0 and /4 to /30.
--------------------	--

Defaults	The default size value is /0.
----------	-------------------------------

Command Modes	DHCP pool configuration
---------------	-------------------------

Command History	Release	Modification
	12.2(8)T	This command was introduced.
	12.3(11)T	The <b>file</b> keyword was added.

Usage Guidelines	If you do not configure the pool as an autogrow pool, the pool will not request additional subnets if one subnet is already in the pool.
------------------	--

Use the **dhcp** keyword to obtain subnets from DHCP, the **aaa** keyword to obtain subnets from the AAA server, and the **ipcp** keyword to obtain subnets from IPCP negotiation. If you expect that the utilization of the pool may grow over time, use the **autogrow size** option.

**origin**

If a pool has been configured with the **autogrow size** option, ensure that the source server is capable of providing more than one subnet to the same pool. Even though the Cisco IOS software specifies the requested subnet size, it can accept any offered subnet size from the source server.

**Examples**

The following example shows how to configure an address pool named green to use DHCP as the subnet allocation protocol with an initial subnet size of 24 and an autogrow subnet size of 24:

```
ip dhcp pool green
  vrf green
  origin dhcp subnet size initial /24 autogrow /24
    utilization mark high 80
    utilization mark low 20
```

The following example shows how to configure the location of the external text file:

```
ip dhcp pool abcpool
  origin file tftp://10.1.0.1/staticbindingfile
```

**Related Commands**

Command	Description
<b>show ip dhcp pool</b>	Displays information about the DHCP address pools.

# Glossary

**address binding**—A mapping between the client IP and hardware addresses. The client IP address may be preconfigured by the administrator (manual address allocation) or assigned from a pool by the Dynamic Host Configuration Protocol (DHCP) server (automatic address allocation).

**address pool**—The range of IP addresses assigned by the DHCP server. The pool may also store client parameters, such as default router and DNS servers.

**client identifier**—A DHCP option that allows clients to be identified with a unique opaque identifier, instead of relying on the hardware address.

**database agent**—Any host storing the DHCP bindings database.

**DHCP client**—Any host requesting configuration parameters.

**DHCP database**—An external file configured in a DHCP server, which stores automatic bindings from the server.

**DHCP server**—Any host providing configuration parameters.



**Note**

---

Refer to *Internetworking Terms and Acronyms* for terms not included in this glossary.

---

CCVP, the Cisco logo, and Welcome to the Human Network are trademarks of Cisco Systems, Inc.; Changing the Way We Work, Live, Play, and Learn is a service mark of Cisco Systems, Inc.; and Access Registrar, Aironet, Catalyst, CCDA, CCDP, CCIE, CCIP, CCNA, CCNP, CCSP, Cisco, the Cisco Certified Internetwork Expert logo, Cisco IOS, Cisco Press, Cisco Systems, Cisco Systems Capital, the Cisco Systems logo, Cisco Unity, Enterprise/Solver, EtherChannel, EtherFast, EtherSwitch, Fast Step, Follow Me Browsing, FormShare, GigaDrive, HomeLink, Internet Quotient, IOS, iPhone, IP/TV, iQ Expertise, the iQ logo, iQ Net Readiness Scorecard, iQuick Study, LightStream, Linksys, MeetingPlace, MGX, Networkers, Networking Academy, Network Registrar, PIX, ProConnect, ScriptShare, SMARTnet, StackWise, The Fastest Way to Increase Your Internet Quotient, and TransPath are registered trademarks of Cisco Systems, Inc. and/or its affiliates in the United States and certain other countries.

All other trademarks mentioned in this document or Website are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (071IR)

Copyright © 2004 Cisco Systems, Inc. All rights reserved.

